


PE SEAL PLACEMENT USING CELL SELECTOR

1. Choose **Utilites** on the Main Menu Bar.
2. Move down the list and choose **Cell Selector**.
3. This will bring up the following Dialog Box:




4. Choose **“File”** and **“Open”** (You may need to select the path as shown above)
5. Choose your Project Group’s **.csf** file from the list of files. Example: pg4.csf (click ok)
6. This will bring up the following Cell Selector Dialog Box as shown below:



7. Next choose the cell that you want to place.

8. This will bring up the *Place Active Cell* Dialog box.



9. For english project set the scale to the inverse of the scale that you are using.

10. For metric project take the Scale Factor that you are using this will be your scale. (only for the PE seal)

